
Tranalyzer2

smtpDecode



Simple Mail Transfer Protocol (SMTP)



Tranalyzer Development Team

CONTENTS

Contents

| l | smt | tpDecode | | | |
|---|-----|----------------------|--|--|--|
| | 1.1 | Description | | | |
| | 1.2 | Configuration Flags | | | |
| | 1.3 | Flow File Output | | | |
| | 1.4 | Packet File Output | | | |
| | 1.5 | Plugin Report Output | | | |
| | | TODO | | | |

1 smtpDecode

1.1 Description

The smtpDecode plugin processes MAIL header and content information of a flow. The idea is to identify certain mail features and CNAMES.

1.2 Configuration Flags

The following flags can be used to control the output of the plugin:

| Name | Default | Description | Flags |
|--------------|-------------------|---|-------------|
| SMTP_SAVE | 0 | 1: save content to SMTP_F_PATH | |
| SMTP_RMDIR | 1 | Empty SMTP_F_PATH before starting | SMTP_SAVE=1 |
| SMTP_BTFLD | 0 | 1: Bitfield coding of SMTP commands | |
| SMTP_RCTXT | 1 | 1: print response code text | |
| SMTP_MXNMLN | 70 | maximal name length | |
| SMTP_MXUNMLN | 25 | maximal user length | |
| SMTP_MXPNMLN | 15 | maximal PW length | |
| SMTP_MAXCNM | 8 | maximal number rec,trans codes | |
| SMTP_MAXUNM | 5 | maximal number server names | |
| SMTP_MAXPNM | 5 | maximal number server names | |
| SMTP_MAXSNM | 8 | maximal number of server addresses | |
| SMTP_MAXRNM | 8 | maximal number of rec EMail addresses | |
| SMTP_MAXTNM | 8 | maximal number of trans EMail addresses | |
| SMTP_F_PATH | "/tmp/SMTPFILES/" | Path for extracted content | |
| SMTP_NONAME | "nudel" | No name file name | |

1.2.1 Environment Variable Configuration Flags

The following configuration flags can also be configured with environment variables (ENVCNTRL>0):

- SMTP_RMDIR
- SMTP_F_PATH
- SMTP_NONAME

1.3 Flow File Output

The smtpDecode plugin outputs the following columns:

| Column | Type | Description | Flags |
|----------|------|------------------------|--------------|
| smtpStat | H8 | Status | |
| smtpCBF | H16 | Command codes bitfield | SMTP_BTFLD=1 |
| smtpCC | RSC | Command codes | |
| smtpRC | RU16 | Response codes | |
| smtpUsr | RS | Users | |

| Column | Type | Description | Flags |
|------------|------|------------------------------------|-------|
| smtpPW | RS | Passwords | |
| smtpSANum | U8 | Number of server addresses | |
| smtpESANum | U8 | Number of email sender addresses | |
| smtpERANum | U8 | Number of email receiver addresses | |
| smtpSA | RS | Server send addresses | |
| smtpESA | RS | Email send addresses | |
| smtpERA | RS | Email receive addresses | |

1.3.1 smtpStat

The ${\tt smtpStat}$ column is to be interpreted as follows:

| smtpStat | Description | Flags |
|---|--|-------------|
| $ \begin{array}{ccc} 2^0 & (=0 \times 01) \\ 2^1 & (=0 \times 02) \\ 2^2 & (=0 \times 04) \\ 2^3 & (=0 \times 08) \end{array} $ | SMTP ports found Authentication pending Data download pending User password pending | SMTP_SAVE=1 |
| 2^4 (=0x10) 2^5 (=0x20) | flow write finished | SMTP_SAVE=1 |
| 2^{6} (=0x40) 2^{7} (=0x80) | File error Array overflow | SMTP_SAVE=1 |

1.3.2 smtpCBF

The smtpCBF column is to be interpreted as follows:

| smtpCBF | Description |
|---------------------------|-------------|
| 2^0 (=0x0001) | HELO |
| 2^1 (=0x0002) | EHLO |
| $2^2 (=0 \times 0004)$ | MAIL |
| 2^3 (=0x0008) | RCPT |
| $2^4 = (-0 \times 0.010)$ | DATA |
| 2^5 (=0x0020) | RSET |
| 2^6 (=0x0040) | SEND |
| 2^7 (=0x0080) | SOML |

1.4 Packet File Output

In packet mode (-s option), the smtpDecode plugin outputs the following columns:

| Column | Type | Description | Flags |
|----------|------|-------------|-------|
| smtpStat | Н8 | Status | |

1.5 Plugin Report Output

The following information is reported:

- Aggregated smtpStat
- Number of SMTP packets
- Number of SMTP files

1.6 TODO

• fragmentation